## How to connect to a SE7EN unit through Windows SEVEN (7)

1. Make sure that your computer is equipped with a Bluetooth device. If not install an USB based similar to the one displayed below.



- 2. Make sure that your Poseidon SE7EN unit is turned on by inserting the battery physically. This is required to set the unit in pair mode.
- 3. Add a device, by a, right click on the Bluetooth icon and then b, selecting "Add a device"



4. Once you press "add a device" per point 3 the screen below will show up. Identify that the Poseidon G2B-XXXXXX matches your serial number. This to prevent from pairing to the incorrect unit if several units are on site. Some versions of the OS might ask for a Bluetooth PIN. If this is the case use PIN "0000" (zero zero zero zero). Once selected, click next

🕞 ず Lägg til en enhet
Välj en enhet som ska läggas till på den här datorn Windows fortsätter att söka efter nya enheter och visar dem häl.
Poseidon G28-00010025 Bluetooth Annan
Vad händer om enheten inte identifieras i Windows?
Něsta Avbryt

5. When the device is installed correctly you will see this screen. To identify the COM port that is attached to your Poseidon SE7EN click devices and printers

	🕞 🖬 Laga tillen enhet	
	Den här enheten har lagts till på den här datom   Windows söker nu efter drivrutiner och kommer att installera dem om det behövs. Du kanske måste vänta tills kontrollen slutförs innan du kan använda enheten.   Om du vill kontrollera om enheten har installerats korrekt söker du efter den i faheter och skrivare.   Desender och skrivare.	
l		

6. When devices and printers appear, right click on the icon that matches your serial number i.ex. G2B-XXXXXXX and press properties.



7. When you've pressed properties the pop up window will look like the picture below. Go to the second tab and identify the COM port used for the Poseidon SE7EN (in this case COM13). This is the port to use in the config tool.



8. Your Bluetooth connection is now configures and it is time to launch the PC software. Once started it will look like the picture below. Go to the settings tab and select serial port.

Select view Select serial not	lē ×	
Unit SE7EN User settings		
Divelog	POSEIDON S	SE'/EN Connect Disconnect
	Status: Ready	
	System	O2 tank
	Version: <not available=""></not>	<not vald=""></not>
	Battery	Diluent tank
	Type: <unknown></unknown>	<not valid=""></not>

9. Press update port button and select the port discovered during step 7 (in this caseCOM13).

	Descional CEREN and
	PUSEIDUN SEVEN Connect Disconnect
BConfig - S	Select port
Update port	COM1 [(Standardporttyper): Kommunikationsport] Cancel   COM10 [Microsoft: Standard Serial over Bluetooth link] Cancel   COM13 [Microsoft: Standard Serial over Bluetooth link] Communikationsport]   COM13 [Microsoft: Standard Serial over Bluetooth link] Communikationsport]   COM13 [Microsoft: Standard Serial over Bluetooth link] Interview Bluetooth link]   COM13 [Microsoft: Standard Serial over Bluetooth link] Interview Bluetooth link]   COM13 [Intel(R) Actagement Technology - SOL] It tank   V Type: <unknown></unknown>
	Seral port: Update port

10. The software is now ready to connect to the Poseidon SE7EN. This is easy, just press the connect button.

alast view	a v		
	0 1		
Divelog		POSEIDON SI	
Divelog			
		Status: Ready	
		System	O2 tank
		Version: <not available=""></not>	<not valid=""></not>
		Battery	Diluent tank
		Type: <unknown></unknown>	<not valid=""></not>

11. The computer now connects to your Poseidon SE7EN (if it is turned on; either by wet switch or by installing the battery) and you can now follow the pre dive sequence in system window, determine your battery type and see cylinder pressures.

lect view 6	F X
velog	Version: v0.53 SN: 10025 Shi to 2013 O2 tank Disconnect   Battery Version: v0.53 Shi to 225 Mer 23 O2 tank Size 3 liter Maximum 130 bar   Battery Version: v0.51 Mer 23 Diuent tank Its bar   Diuent tank Size 3 liter Maximum 200 bar 145 bar